

3.1.1 Drive camera

Common API functions used by OpenCV:

1. cv2.VideoCapture()

cap = cv2.VideoCapture(0)

The parameter in VideoCapture () is 0, which means Raspberry Pi video0.

(Note: You can view the current camera through the command Is/dev/)

pi@raspberrypi:~	S ls /dev/	mough the c	ommand <mark>13/0</mark>	icv _/)
argon-h264mem	media1	shm	tty38	vcio
argon-hevcmem	mem	snd	tty39	vc-mem
argon-intcmem	memory bandwidth	spidev0.0	The same of the sa	VCS
argon-vp9mem	mmcblk0	spidev0.1		vcs1
autofs	mmcblk0p1	stderr	tty41	vcs2
block	mmcblk0p2	stdin	tty42	vcs3
btrfs-control	mqueue	stdout	tty43	vcs4
bus	net	tty	tty44	vcs5
cachefiles	network latency	tty0	tty45	vcs6
char	network throughput	The second second	tty46	vcs7
console	null	tty10	tty47	vcsa
cpu dma latency		tty11	tty48	vcsal
cuse	ppp	tty12	tty49	vcsa2
disk	ptmx	tty13	tty5	vcsa3
dri	pts	tty14	tty50	vcsa4
fb0	ram0	tty15	tty51	vcsa5
fd	ram1	tty16	tty52	vcsa6
full	ram10	tty17	tty53	vcsa7
fuse	ram11	tty18	tty54	vcsm
gpiochip0	ram12	tty19	tty55	vcsm-cma
gpiochip1	ram13	tty2	tty56	vcsu
gpiochip2	ram14	tty20	tty57	vcsul
gpiomem	ram15	tty21	tty58	vcsu2
hwrng	ram2	tty22	tty59	vcsu3
i2c-1	ram3	tty23	tty6	vcsu4
initctl	ram4	tty24	tty60	vcsu5
input	ram5	tty25	tty61	vcsu6
kmsg	ram6	tty26	tty62	vcsu7
log	ram7	tty27	tty63	vga_arbiter
loop0	ram8	tty28	tty7	vhci
loop1	ram9	tty29	tty8	video0
loop2	random	tty3	tty9	video1
loop3	raw	tty30	ttyAMA0	video10
loop4	rfkill	tty31	ttyprintk	
loop5	rpivid-h264mem	tty32	ttyS0	video12
loop6	rpivid-hevcmem	tty33	uhid	watchdog
loop7	rpivid-intcmem	tty34	uinput	watchdog0
loop-control	rpivid-vp9mem	tty35	urandom	zero
mapper	serial0	tty36	v41	
media0	serial1	tty37	vchiq	

cap = cv2.VideoCapture(".../1.avi")

VideoCapture(".../1.avi"), This parameter indicates that if the path of the video file is entered, the video is opened.

2.cap.set()

Camera parameters common configuration methods:

```
capture.set(CV_CAP_PROP_FRAME_WIDTH, 1920); # Width
capture.set(CV_CAP_PROP_FRAME_HEIGHT, 1080); # Height
```



```
capture.set(CV_CAP_PROP_FPS, 30);  # Frame
capture.set(CV_CAP_PROP_BRIGHTNESS, 1);  # Brightness 1
capture.set(CV_CAP_PROP_CONTRAST, 40);  # Contrast 40
capture.set(CV_CAP_PROP_SATURATION, 50);  # Saturation 50
capture.set(CV_CAP_PROP_HUE, 50);  # Hue 50
capture.set(CV_CAP_PROP_EXPOSURE, 50);  # Visibility 50
```

Parameter explanation:

```
#define CV CAP PROP POS MSEC 0
// Calculate the current position in milliseconds
#define CV CAP PROP POS FRAMES
// Calculate the current position in frame
#define CV CAP PROP POS AVI RATIO 2 // Relative position of the video
#define CV CAP PROP FRAME WIDTH 3 // Width
#define CV CAP PROP FRAME HEIGHT 4 // Height
#define CV CAP PROP FPS
                              5
                                 // Frame rate
#define CV CAP PROP FOURCC
                                 6 // 4 Character encoding
#define CV CAP PROP FRAME COUNT 7 // Video frames
#define CV CAP PROP FORMAT
                                 8 // Video format
#define CV_CAP_PROP_MODE
// Backend specific value indicating the current capture mode.
#define CV CAP PROP BRIGHTNESS 10 // Brightness
#define CV CAP PROP CONTRAST 11 // Contrast
#define CV CAP PROP SATURATION 12 // Saturation
#define CV CAP PROP HUE
                               13 // Hue
#define CV CAP PROP GAIN
                               14 // Gain
#define CV CAP PROP EXPOSURE
                                 15 // Exposure
#define CV CAP PROP CONVERT RGB 16
// Mark whether the image should be converted to RGB.
#define CV CAP PROP WHITE BALANCE 17 // White balance
#define CV_CAP_PROP_RECTIFICATION 18 // Stereo camera calibration mark (note:
only support DC1394 v2)
```

3.cap.isOpened()

Return true indicates open camera successful and false indicates open camera failure

4.ret,frame = cap.read()

cap.read () reads the video frame by frame. ret and frame are the two return values of the cap.read () function.

ret is a Boolean value, if the read frame is correct, it will return true, If the file has not been read to the end, it returns False.

Frame is the image of each frame, which is a three-dimensional matrix.

5.cv2.waitKey(n)



n represents the delay time, if the parameter is 1, it means a delay of 1ms to switch to the next frame of image.

If the parameter is too large, such as cv2.waitKey (1000), it will freeze because of the long delay.

The parameter is 0, such as, cv2.waitKey (0) only displays the current frame image, which is equivalent to video pause.

6.cap.release() and destroyAllWindows()

Call cap.release () to release the video.

Call destroyAllWindows () to close all image windows.

About Code

Since our entire tutorial runs in JupyterLab, we must understand the various components inside.

Here we need to use the image display component.

1.Import library

import ipywidgets.widgets as widgets

2.Set Image component

image widget = widgets.Image(format='jpeg', width=600, height=500)

3. Display Image component

display(image_widget)

4. Open camera and read image

image = cv2.VideoCapture(0) # Open camera
ret, frame = image.read() # Read camera data

5. Assignment to components

#Convert the image to jpeg and assign it to the video display component

image_widget.value = bgr8_to_jpeg(frame)

import cv2

import ipywidgets.widgets as widgets

import threading

import time

#Set camera display component

image widget = widgets.Image(format='jpeg', width=600, height=500)

display(image_widget) # display camera component

#bgr 8 to jpeg format

import enum

import cv2



```
def bgr8_to_jpeg(value, quality=75):
    return bytes(cv2.imencode('.jpg', value)[1])
image = cv2.VideoCapture(0)
                                    # Open camera
# width=1280
# height=960
# cap.set(cv2.CAP PROP FRAME WIDTH, width) # set width of image
# cap.set(cv2.CAP_PROP_FRAME_HEIGHT,height) # set height of image
image.set(3,600)
image.set(4,500)
image.set(5, 30) # set frame
image.set(cv2.CAP PROP FOURCC, cv2.VideoWriter.fourcc('M', 'J', 'P', 'G'))
image.set(cv2.CAP PROP BRIGHTNESS, 40) #set brightness -64 - 64 0.0
image.set(cv2.CAP_PROP_CONTRAST, 50) #set contrast -64 - 64 2.0
image.set(cv2.CAP_PROP_EXPOSURE, 156) #set exposure value 1.0 - 5000 156.0
ret, frame = image.read()
                             # read camera data
image widget.value = bgr8 to jpeg(frame)
while 1:
    ret, frame = image.read()
    image_widget.value = bgr8_to_jpeg(frame)
    time.sleep(0.010)
image.release()
                 #After using the object, we need to release the object, otherwise
```

when we use the object again, the system will prompt that the object be occupied, making it unusable.

The camera screen is shown below:

